



Turbo-BASIC XL 1.5
© 1985 Frank Ostrowski

Expanded

Turbo-BASIC XL

Documentation

by Ron Fetzer

Introduction:

This expanded documentation is based on the pioneering work of Dave and Laura Yearke of the Western New York Atari Users Group.

The superb Turbo-BASIC XL by Frank Ostrowski from Germany works only on the Atari XL and Atari XE computers. It is completely compatible with Atari BASIC. In addition to the regular Atari BASIC commands you get 42 more commands and 22 more functions. You have a useable RAM of 34,021 bytes. This is 1,747 more bytes than Atari BASIC. It runs 3 times faster than Atari BASIC and you have a BASIC COMPILER that increases the speed 10 to 15 times more.

The DOS commands are accessed in the direct mode or the programmed mode. There is no Turbo-BASIC XL DOS. You have new graphics commands not available before. Turbo-BASIC XL is insensitive to upper or lower or inverse characters for most of its commands. You can have 256 variable names.

This documentation tries to provide programming examples for the new commands. There is an index at the end of this documentation for easy finding of commands.

Loading Turbo-BASIC XL:

Turbo-BASIC XL gets loaded without a cartridge.

1. Turn on your disk drive.
2. Insert the Turbo-BASIC XL disk.
3. On the XE hold down the OPTION key and turn on the computer.

Disk Commands:

The DOS functions are accessed in the direct or the programmed mode. There is no Turbo-DOS. If you type DOS you are directed to DOS 2.5. You are now out of Turbo-BASIC XL. It is suggested that you save your program first otherwise it is lost. You can get back into Turbo-BASIC XL by using OPTION L on the DOS and typing AUTORUN.SYS for the file name.

```
BLOAD          FORMAT:      BLOAD "D:name"  
                  EXAMPLE:    BLOAD "D:TEST.BIN"
```

This command is used to load binary files. The file will automatically load without having to give a memory address. It is just like Option L with /N on DOS 2.0.

```
BRUN           FORMAT:      BRUN "D:name"  
                  EXAMPLE:    BRUN "D:COMPILER.COM"
```

This is used to load and RUN a machine language (Binary) file. The file will run automatically without having to give a memory address. It is the same as Option L and Option M on DOS 2.0.

```
DELETE        FORMAT:      DELETE "D:name"  
                                     (Wild cards are O.K.)  
                  EXAMPLE:    DELETE "D:TEST.BAS"  
                               DELETE "D8:test.bas"  
                               delete "D2:*.*"  
                               Delete "D2:TEST.???"  
                               90 DELETE "D:*.*"
```

This command erases from the disk a file specified. The wild card symbols (*. * and ???) are permitted. The device name (D:) has to be in capital letters. Inverse file names are not permitted. In the programmed mode it has to be the last item on the line. This is the same as Option D on DOS 2.0.

Disk Commands (Cont.):

DIR FORMAT: DIR (Wild cards O.K.)
 EXAMPLE: DIR
 DIR "D:*.*"
 DIR "D2:*.*BAS"
 DIR "D:???.*"
 DIR "D8:*.*"
 90 DIR "D8:*.*"

This command gives you the disk directory. Wild cards are permitted. In the programmed mode it has to be the last item on the line. This is the same as Option A on DOS 2.0.

RENAME FORMAT: RENAME "D:old name,new name"
 EXAMPLE: RENAME "D:FILE.OLD,FILE.NEW"
 RENAME "D8:*.*TXT,*.*BAS"

This command renames a file. The first name is the OLD name, the second name is the NEW name. The comma between them is important. Wild cards are permitted. This is the same as Option E on DOS 2.0.

LOCK FORMAT: LOCK "D:name"
 EXAMPLE: LOCK "D:TEST.BAS"
 LOCK "D2:SCREEN.???"
 LOCK "D8:*.*"
 90 LOCK "D:*.*"

This command locks a file so you cannot change it or erase it until you unlock it. Wild cards are permitted. In the programmed mode it has to be the last item on the line. This is the same as Option F on DOS 2.0.

UNLOCK FORMAT: UNLOCK "D:name"
 EXAMPLE: UNLOCK "D:TEST.BAS"
 UNLOCK "D2:SCREEN.???"
 UNLOCK "D8:*.*"
 10 UNLOCK "D:*.*"

This command is the opposite of LOCK. It opens a file so it can be changed. Wild cards are permitted. In the programmed mode it has to be the last item on the line. This is the same as Option G on DOS 2.0.

Memory:

DPOKE FORMAT: DPOKE m,v
 EXAMPLE: DPOKE 88,32750
 90 DPOKE 88,32750

This command puts 2 bytes of data into 2 consecutive memory locations. In the example above at POKE 88 and POKE 89 integer 32750 is stored.

DPEEK FORMAT: DPEEK (m)
 EXAMPLE: ? DPEEK (88)
 90 ? DPEEK (88)

This is the opposite of DPOKE. It retrieves a 2 byte integer from 2 consecutive locations. In the example above at PEEK (88) and PEEK (89).

MOVE FORMAT: MOVE m,m1,m2
 EXAMPLE: MOVE 53248,32768,1024
 MOVE \$D000,\$8000,\$400

This moves a whole block of data. The 'm' is the old address, the 'm1' is the new address and the 'm2' is the length of the data in bytes.

-MOVE FORMAT: -MOVE m,m1,m2
 EXAMPLE: -MOVE 53248,32768,1024
 -MOVE \$D000,\$8000,\$400

This is the same as above except it copies starting with the last byte of the block.

BPUT FORMAT: BPUT #n,adr,len
 EXAMPLE: BPUT #3,ADR(B\$),LEN(B\$)

EXAMPLE #2

```
100 CLS
110 GRAPHICS 5:ADDR=DPEEK(88)
120 PRINT "    FILL THE SCREEN"
130 FOR X = 1 TO (20*40)
140   POKE ADDR+X,RAND(125)
150 NEXT X
160 ? "Now BPUT data onto RAMDISK D8:SCREEN"
170 CLOSE:OPEN #1,8,0,"D8:SCREEN"
180 BPUT #1,ADDR,20*40
190 CLOSE
200 ? "IT IS DONE!"
210 FOR Y= 1 TO 6000:NEXT Y
220 GRAPHICS 0
```

This outputs a block of data to a device specified by the channel number (1-7). The block starts at 'adr' and ends at 'len'. In the example above we wrote to the RAM DISK the screen data under the file name "SCREEN". It can be recovered with BGET. See the next command.

Memory (Cont.):

BGET FORMAT: BGET #n,adr,len
EXAMPLE: BGET #3,ADR(B\$),LEN(B\$)

EXAMPLE #2

```
100 CLS
110 GRAPHICS 5:ADDR=DPEEK(88)
120 CLOSE:OPEN #1,4,0,"D8:SCREEN"
130 ? "BGET data from RAM DISK D8:'SCREEN'"
140 BGET #1,ADDR,20*40
150 CLOSE
160 FOR Y=1 TO 6000:NEXT Y
170 GRAPHICS 0
```

BGET recovers a block of data saved with BPUT. The '#n' is the channel number (1-7), 'adr' is the memory address and 'len' is the length of the data.

%PUT FORMAT: %PUT #n,a
EXAMPLE: %PUT #1,A

EXAMPLE #2

```
10 CLS
20 CLOSE:OPEN #1,8,0,"D8:TEST"
30 FOR X = 1 TO 5
40     INPUT "GIVE ME A NUMBER>",&A
50     %PUT #1;&A
60 NEXT X:CLOSE
70 ?:? "I have saved the numbers with %PUT to the RAM DISK under 'TEST'"
80 ??:DIR "D8:*.*)"
```

This is the same as 'PRINT #1;&A' except it is much faster and uses less memory. You must open a channel for %PUT. See the demonstration program on the front of this disk. Use RUN "D:PUTGET.TUR". If you have a XL computer list the program and change all references from D8: to D1: and then run it. You can retrieve the numbers in EXAMPLE #2 by using the %GET program that follows. It is used with NUMBERS only.

%GET FORMAT: %GET #n,a
EXAMPLE: %GET #1,A

EXAMPLE #2

```
10 CLS
20 CLOSE:OPEN #1,4,0,"D8:TEST"
30 FOR Y = 1 TO 5
40     %GET #1;&A
50     ? &A
60 NEXT Y:CLOSE
70 ?:? "I have retrieved the numbers saved with %PUT by using %GET"
80 LIST
```

It retrieves the numbers saved with %PUT. You must have a channel open. It is the same as 'INPUT #1;&A' except it is much faster.

General Programming:

CLS FORMAT: CLS
 EXAMPLE: CLS
 10 CLS

EXAMPLE #2

```
10 CLS
20 FOR X=1 TO 50
30   ? " CLEAR SCREEN ";
40 NEXT X
50 GOTO 10
```

This command clears the screen. It is the same as pressing CNTRL+CLEAR or ? CHR\$ (125).

CLS # FORMAT: CLS #n (channels 1-7)
 EXAMPLE: CLS #3
 90 CLS #3

EXAMPLE #2

```
10 CLS
20 ?::?:?:?:?:? "THIS WILL NOT BE ERASED - IT IS BEFORE LINE 30 (OPEN) .
   TO STOP-->'BREAK'"
30 CLOSE:OPEN #3,4,0,"K:"
40 CLS #3
50 ? "PRESS ANY KEY";
60 GET #3,L
70 ?::? "YOU PRESSED THE ";CHR$(L);" KEY":?
80 CLS #3
90 GOTO 40
```

This command clears the screen of any information that was there because of the opened channel. This is different from CLS which clears the whole screen.

PAUSE FORMAT: PAUSE n
 EXAMPLE: PAUSE 50
 90 PAUSE 100

EXAMPLE #2

```
10 CLS
20 REPEAT:A=A+1
30   ? A;"", ";
40   PAUSE 100
50 UNTIL A=20
```

EXAMPLE #3

```
10 CLS
20 X=10
30 REPEAT:A=A+1
40   ? A;"", ";
50   PAUSE 10*X
60 UNTIL A=20
```

This command puts a time delay of about 1/60 of a second into your program for each number. PAUSE 60 = about 60/60 or 1 second delay. It is the similar to 'FOR X = 1 TO 60:NEXT X'. Computed values are allowed. Negative values are not allowed.

General Programming (Cont.):

RENUM FORMAT: RENUM n,i,j
 EXAMPLE: RENUM 10,100,10
 90 RENUM 100,10,10

EXAMPLE #2

```
10 CLS
20 ? "RENUMBER PLEASE!"
30 PAUSE 100
40 LIST
50 RENUM 10,100,20
60 LIST
```

EXAMPLE #3

```
10 CLS
20 X=3
30 ? " HELLO ";
40 GOTO X*10
50 REM X*10 WILL NOT BE RENUMBERED
60 RENUM 10,100,20
70 LIST
```

This command renumbers your program. The 'n' is the program line number that you want to start renumbering with. The 'i' is the first NEW number. The 'j' is the increment. It will not renumber line references which involve variables or computed values. See example #3.

DEL FORMAT: DEL n,i
 EXAMPLE: DEL 60,100
 90 DEL 50,80

EXAMPLE #2

```
10 CLS
20 ? "THIS LINE STAYS"
30 ? "30 GOES"
40 ? "40 GOES"
50 ? "50 GOES"
60 DEL 30,50
70 LIST
```

This command deletes lines out of your program. 'n' = the starting number and 'i' = the ending number. It can be used in the direct or programmed mode.

General Programming (Cont.):

DUMP FORMAT: DUMP
 EXAMPLE: DUMP
 90 DUMP

EXAMPLE #2

```
10 CLS
20 DIM A$(35),B(5)
30 A$="DUMP - VARIABLES AND THEIR VALUES"
40 REPEAT:X=X+1
50     INPUT "GIVE ME A NUMBER>",C
60     B(X)=C:REM NUMBER ARRAY
70 UNTIL X=5
80 ? "     NUMBERS"
90 FOR T = 1 TO 5
100    ? B(T)
110 NEXT T
120 ??:A$
130 DUMP
```

This command dumps the variables used and their values. For numeric arrays the DUMPed value will be shown as: B(6,1. The DUMPed value is the DIMed value +1. String values are shown with their length first and then their DIMed value. PROCEDURE names and labels and their line values are also listed. The NEW command clears the DUMPed values. This command can be used in the direct or the programmed mode.

DUMP Dn FORMAT: DUMP name
 EXAMPLE: DUMP "P:"
 DUMP "D8:VARIB"
 90 DUMP "P:"

EXAMPLE #2

```
10 CLS
20 DIM A$(40),B(5)
30 A$="DUMPed - VARIABLES"
40 FOR X = 1 TO 5
50     INPUT "GIVE ME A NUMBER>",C
60     B(X)=C:REM NUMBER ARRAY
70 NEXT X
80 FOR Y = 1 TO 5
90     ? B(Y):LPRINT B(Y)
100 NEXT Y
110 LPRINT:LPRINT A$
120 DUMP "P:"
```

This command is the same as above except we DUMP to a device specified. "P:" = printer or "D8:VARIB" = Ram Disk. For example #2 turn on your printer. This command can be used in the direct or the programmed mode.

General Programming (Cont.):

TRACE FORMAT: TRACE
 TRACE -
 EXAMPLE: 10 TRACE
 90 TRACE -

EXAMPLE #2

```
10 TRACE
20 CLS
30 ?:? "   TRACING"
40 REPEAT:A=A+1
50   ? A; ", ";
60 UNTIL A=10
70 TRACE -
80 ?:?
90 ? "   NO TRACING"
100 REPEAT:B=B+1
110   ? B; ", ";
120 UNTIL B=10
```

This command tells you what line is about to be executed. It is shown in [] on the screen. The TRACE is the way you turn it ON. The TRACE - is the way you turn it OFF. This is a great aid in de-bugging a program.

INPUT FORMAT: INPUT "text";a,b...
 INPUT "text >",a,b...
 EXAMPLE: 20 INPUT "Numbers";A
 50 INPUT "Names";B\$
 70 INPUT "Names &"Ages >>",A\$,B
 90 INPUT "ADDRESS >",ADR\$

EXAMPLE #2:

```
10 CLS
20 DIM A$(10)
30 ? "THIS WILL PRINT ?":?
40 FOR X = 1 TO 3
50   INPUT "Names";A$
60 NEXT X
70 ?:?
80 ? "No Symbol - Use your own":?
90 FOR Y = 1 TO 3
100   INPUT "Numbers >>",B
110 NEXT Y
```

This command lets you use a prompt with the INPUT for easier programming. If you use a semicolon after the prompt the usual '?' will be printed. If you use a comma after the prompt nothing will be printed and you have to include your own symbol with the prompt. See example #2.

General Programming (Cont.):

GO TO FORMAT: GO TO
 EXAMPLE: 50 GO TO 20
 GO TO 100

EXAMPLE #2

```
10 CLS
20 ? " HELLO ";
30 GO TO 20
```

This command is the same as the usual GOTO.

***L** FORMAT: *L (DEFAULT)
 *L -
 EXAMPLE: 30 *L
 90 *L -

EXAMPLE #2

```
10 CLS:??
20 *L
30 ? "LINE # 50-70 INDENT ON"
40 FOR X = 1 TO 5
50     ? " ";
60     ? " ";
70     ? " ";
80 NEXT X
90 LIST
100 PAUSE 300
110 CLS:??
120 *L -
130 ? "LINE # 50-70 INDENT OFF"
140 LIST
```

When listing a program with loops this command either turns on the indent on the loops or turns them off. The *L turns it ON. This is the normal default condition. The *L - turns the indent OFF. This works not only on the screen but also on the printer.

General Programming (Cont.):

***F** FORMAT: *F (or *F+)
 *F -
 EXAMPLE: 70 *F
 90 *F -

EXAMPLE #2

```
10 CLS
20 ? "ILLEGAL REVERSE LOOP":?
30 FOR X = 2 TO 1
40   ? X
50 NEXT X
60 PAUSE 200
70 *F
80 ?:"ILLEGAL LOOP - NO EXECUTION - '*F'"
90 FOR X = 2 TO 1
100  ? X
110 NEXT X
120 PAUSE 200
130 LIST
```

Atari BASIC has a bug. It allows execution of an illegal reverse loop. (FOR X=2 TO 1:? X:NEXT X). This command allows you to turn this feature off or on. *F or *F + turns it OFF. *F - turns the bug ON if you want it.

***B** FORMAT: *B (or B+)
 *B -
 EXAMPLE: 90 *B
 200 *B -

EXAMPLE #2

```
10 CLS:?
20 CLOSE:OPEN #1,8,0,"D8:TEST"
30 FOR X=1 TO 3
40   INPUT "GIVE ME A NUMBER";A
50   %PUT #1;A
60 NEXT X:CLOSE
70 PAUSE 100:?:?
80 ? " I AM TRAPPING 'BREAK' KEY"
90 *B
100 CLOSE:TRAP 180:OPEN #1,4,0,"D8:TEST"
110 ?:"
120 FOR Y = 1 TO 3
130   PAUSE 100
140   %GET #1;A
150   ? A;" TRY BREAK KEY"
160 NEXT Y:CLOSE
170 END
180 REM TRAP
190 ?:"BREAK KEY TRAPPED!"
200 GOTO 90
```

This command lets you trap the break key so your program cannot accidentally be stopped by hitting the BREAK key. This command works with the TRAP command. The *B turns it ON. The *B - turns it OFF.

General Programming (Cont.):

```
--          FORMAT:      --
          EXAMPLE:      10 --
                          90 --
```

EXAMPLE #2

```
10 --
20 CLS
30 ? " 30 DASHES "
40 ? " HELLO "
50 --
60 LIST
```

This command prints 30 dashes across the screen or the page when you LIST your program. It can be used to make your program listing clearer.

```
DSOUND      FORMAT:      DSOUND n, f, d, v
                          DSOUND
          EXAMPLE:      10 DSOUND 1, 72, 12, 8
                          90 DSOUND
```

EXAMPLE #2

```
10 CLS
20 ?:"PRESS 'RESET' TO STOP"
30 X = RAND(255)
40 ? X;" ";
50 DSOUND 1, X, 12, 8
60 PAUSE 25
70 DSOUND
80 DSOUND 0, X, 12, 8
90 GOTO 30
```

This command pairs channels for increased frequency range and resolution. n=channels (0 or 1). f=frequency range (0-65535). d=distortion (0-15) 10 and 14 produce pure tones. v=volume (0-15). 0 is silent 15 is the loudest. DSOUND turns all sound OFF.

Line Labels:

```
#          FORMAT:      # name
          EXAMPLE:      120 # END
                          120 # END_OF_FILE

                          EXAMPLE #2

10 CLS
20 CLOSE:OPEN #1,8,0,"D8:TEST"
30 REPEAT:X=X+%1
40     INPUT "GIVE ME A NUMBER";A
50     %PUT #1,A
60 UNTIL X=%3
70 CLOSE
80 CLOSE:OPEN #1,4,0,"D8:TEST"
90 TRAP # END:%GET #1,A
100 ? A
110 GOTO 90
120 # END:IF ERR=136 THEN CLOSE
```

This command gives the line number that has the '#' the VARIABLE LABEL that follows the '#'. For example: '120 # END' will now become a VARIABLE LABEL and it will be in the variable name table listed as such (Use DUMP to see it). In example #2 see line #90 '90 TRAP # END...'. It will go to line 120. This is the same as if we wrote '90 TRAP 120...' except it is clearer the first way. When there is an EOL error (136) channel #1 will be closed so no error is printed.

A better way would have been '120 # END_OF_FILE...' The underscore () is allowed in variables and labels and makes for clearer listings. We would have a better description of WHERE and WHAT the program does if we had used it. If you use line labels they can be renumbered. %1 and %3 in line 30 and 60 are used because they save us 6 bytes each and stand for the number 1 and 3. See discussion on constants.

```
GO#       FORMAT:      GO# name
          EXAMPLE:      60 GO# GET_KEY 100 GO# ERROR

                          EXAMPLE #2

10 CLS
20 ?:? "PRESS ANY KEY"
30 CLOSE:OPEN #1,4,0,"K:"
40 # GET_KEY:GET #1,A
50 ? CHR$(A);", ";
60 GO# GET_KEY
```

This is the same as GOTO except the GO# looks for a label. You cannot have a space between the GO and #. For the () in line 40 see '# name' above. Line 40 has the variable label of '# GET_KEY'. Line 60 looks for this label and it works just like a GOTO except the listing is clearer.

Modification of Atari Commands:

CLOSE FORMAT: CLOSE
 EXAMPLE: 90 CLOSE
 120 CLOSE:OPEN #1,4,0,"D8:TEST"

This command closes ALL opened channels. It is a good practice to close a channel first before opening it. This command is the same as 'FOR X=1 TO 7:CLOSE X:NEXT X'.

DIM FORMAT: DIM a(n)
 EXAMPLE: 10 DIM A(6)
 30 DIM B\$(20)

This command automatically assigns a value of 0 to all elements in a numeric array and null characters to all elements of a string. The LEN function is still variable and initially 0.

GET FORMAT: GET name
 EXAMPLE: 20 GET A
 90 GET K

EXAMPLE #2

```
10 CLS:?:?  
20 GET A  
30 ? "The key is ";CHR$(A);  
40 ? " the ATASCII = ";A  
50 GOTO 20
```

This command returns the ATASCII value of the key pressed. It is the same as 'OPEN #1,4,0,"K":GET #1;A:CLOSE #1'. The command waits for a key press and assigns the ATASCII value to the variable.

LIST FORMAT: LIST n,
 EXAMPLE: LIST 90,

This command lists the program from the line specified to its end provided the comma is used.

ON/EXEC FORMAT: ON a EXEC n1,n2,...
 EXAMPLE: 30 ON X EXEC START,MAIN_PROG,ENDING

This command is the same as 'ON...GOSUB' except it is used with PROCEDURE. The command executes the PROCEDURES named. Instead of 'ON X GOSUB 200,300,400' we use variable label names of the PROCEDURES. See PROCEDURES.

Modification of Atari Commands (Cont.):

ON/GO# FORMAT: ON a GO# n1,n2,...
EXAMPLE: 70 ON X GO# NORMAL,UPSIDE_DOWN

EXAMPLE #2

```
10 CLS:DIM A$(1)
20 ?:?
30 INPUT "Normal or Upside down";A$
40 IF A$(1,1)="N" THEN X=1
50 IF A$(1,1)<>"N" THEN X=2
60 ?:?
70 ON X GO# NORMAL,UPSIDE_DOWN
80 # NORMAL
90 POKE 755,2
100 ? "THIS IS PRINTED NORMALLY"
110 GOTO 20
120 # UPSIDE_DOWN:CLS
130 POKE 755,7:???:?
140 ? "THIS IS PRINTED UPSIDE DOWN"
150 PAUSE 200:POKE 755,2
160 GOTO 20
```

This command is the same as ON...GOTO except we use variable label names instead of line numbers. In example #2 see line 70.

POP FORMAT: POP
EXAMPLE: 100 POP

EXAMPLE #2

```
10 CLS:???:?
20 GOSUB 50
30 ? "I am the next line"
40 END
50 REM SUBROUTINE
60 POP
70 GOTO 90
80 RETURN
90 ? "I POPPED the RETURN line 30"
100 LIST
```

The POP command will work with all 4 loops, the DO-LOOP, WHILE-WEND, FOR-NEXT and GOSUB. When Turbo-BASIC XL sees a DO, WHILE, FOR or GOSUB it saves its RETURN address on the runtime stack so it knows to what line to return to. If you want BASIC to 'FORGET' this return line use POP. Too many POPs can lead to errors and make for poor programming.

Modification of Atari Commands (Cont.):

PUT FORMAT: PUT n
EXAMPLE: 60 PUT 90
 20 PUT 89,69,83

EXAMPLE #2

```
10 REM SIMPLE WORDPROCESSOR
20 CLS:?
30 OPEN #1,4,0,"K:"
40 GET #1;A:R=R+1
50 IF R=37 THEN ? CHR$(155):R=0
60 PUT A
70 GOTO 40
```

This command is the same as 'PRINT CHR\$(A)'. It takes the ATASCII number and converts it into a character.

RESTORE # FORMAT: RESTORE #name
EXAMPLE: 120 RESTORE #AGAIN
 160 RESTORE #NUM_AGAIN

EXAMPLE #2

```
10 CLS:?
20 DATA 1,2,3,4,5
30 # AGAIN
40 DATA 6,7,8,9,0
50 READ A
60 IF A=0 THEN 100
70 ? A;"", ";
80 PAUSE 10
90 GOTO 50
100 ?:" "NOW DOING LN 40 DATA AGAIN"
110 PAUSE
120 RESTORE #AGAIN
130 READ A
140 IF A=0 THEN 170
150 ? A;"", ";
160 GOTO 130
170 ? :LIST
```

This command moves the data pointer back to the variable label in the DATA chain. In example #2 the RESTORE printed only the numbers in DATA ln. 40 because it came after '30 #AGAIN'. It did not start with ln. #20. It is the same as RESTORE 40 except we use a variable label for clearer programming. The 0 was the flag. When the READ saw a 0 then the IF-THEN came in and directed it to some other line.

Modification of Atari Commands (Cont.):

RND FORMAT: RND
EXAMPLE: 20 RND
 40 X=RND
 90 X=INT (RND*10)
 100 X=INT (RND*10)+1
 200 X=INT (RND*100)

EXAMPLE #2

```
10 X=RND
20 ? X;"", ";
30 GOTO 10
```

EXAMPLE #3

```
10 CLS: ?
20 X=INT (RND*10)
30 PAUSE 25: ? X;"", ";
40 GOTO 20
```

In this command the dummy variable (0) has been eliminated. You can still use the Atari way RND (0) if you want to. In the example ln. 90 you get random numbers from 0-9. In ln. 100 you get random numbers from 1-10. In ln. 200 you get random numbers from 0-99.

RAND (n) FORMAT: RAND (n)
EXAMPLE: 10 X = RAND (10)
 90 X = RAND (100)

EXAMPLE #2

```
10 CLS
20 X = RAND (100)
30 ? X;"", ";
40 PAUSE 25
50 GOTO 20
```

In this command the random numbers are printed as integers. They start with 0 and end with the number-1 in the parentheses.

SOUND FORMAT: SOUND
EXAMPLE: 90 SOUND

EXAMPLE #2

```
10 R=R+1
20 Y = RAND (255)
30 SOUND 0, Y, 10, 8
40 PAUSE 100
50 SOUND
60 X = RAND (255)
70 SOUND 1, X, 12, 8
80 PAUSE 50
90 SOUND
100 IF R=8 THEN SOUND:R=0:GOTO 120
110 GOTO 10
120 END
```

This command turns all sounds off. It is the same as 'SOUND 0,0,0,0.

Modification of Atari Commands (Cont.):

```
TRAP #          FORMAT:      TRAP #name  
                EXAMPLE:    90 TRAP #END  
                            95 TRAP #END_OF_FILE
```

This command is the same as '90 TRAP 150' except it uses variable label names. For an application see example #2 on the command '#name'.

Strings and Errors:

TIME FORMAT: TIME
EXAMPLE: 95 ? TIME/60

EXAMPLE #2

```
10 CLS:???:?
20 ? "TIMING A LOOP":???:?
30 S=TIME:REM STARTING TIME
40 FOR X=1 TO 120:? X;"", "":NEXT X
50 E=(TIME-S)/60:REM E=ELAPSED TIME-S, STARTING TIME
60 ?:?:? INT(E*100)/100;" SECONDS"
```

The TIME counter is active as soon as you turn on your computer. It counts 60 numbers per second. To get a readout in seconds use TIME/60. To get a readout in minutes use TIME/3600. To get a readout in hours use TIME/216000. The TIME counter will continue as long as your computer is turned on. If you want to start the time counter from the beginning then press the RESET button.

TIME\$ FORMAT: TIME\$
EXAMPLE: 30 ? TIME\$

EXAMPLE #2

```
10 CLS:???:?
20 DIM T$(6)
30 INPUT "SET TIME - HHMMSS";T$
40 INPUT "WHEN TO STOP - HHMMSS";S
50 CLS
60 TIME$=T$
70 REPEAT
80     POKE 755,0:REM NO CURSOR
90     POSITION 10,10:? "HOURS,MIN,SEC:";:? TIME$
100    X=VAL(TIME$)
110 UNTIL X=S
120 POSITION 10,12:? "RING! RING! RING!"
130 POKE 755,3:REM CURSOR
```

This command prints the time of day in the form of HOUR MINUTE SECOND (HHMMSS). In Europe they use 50 cycle current and European ATARI's run on this current as against 60 cycle in the USA. As a result of this the TIME\$ function is not accurate and gains 10 minutes each hour.

Strings and Errors (Cont.):

```
INKEY$      FORMAT:      INKEY$
              EXAMPLE:    70 ? INKEY$
                        90 A$=INKEY$

              EXAMPLE #2

10 REM SCREEN WRITER
20 ? INKEY$;
30 GOTO 20

              EXAMPLE #3

10 CLS:DIM A$(1):??:REM GAME
20 ? "HIT THE KEY OF THE LETTER ON THE SCREEN!"
30 PAUSE 150
40 R=RAND(90):IF R<65 THEN 40
50 CLS:POSITION 19,12:? CHR$(R)
60 PAUSE 55
70 A$=INKEY$
80 IF A$=CHR$(R):GOTO 90:ELSE:GOTO 100:ENDIF
90 ?:"YOU GOT IT!":PAUSE 90:GOTO 40
100 ?:"YOU MISSED IT!":PAUSE 90:GOTO 40
```

This command returns the character of the last key hat was pressed. In example #3 please note line 70. Line 80 uses and IF-ELSE-ENDIF command.

```
INSTR      FORMAT:  INSTR(x$, a$, i)
              EXAMPLE: 50 ? INSTR(X$, A$, 1)

              EXAMPLE #2

10 DIM X$(30), A$(5)
20 X$="MY HEART BELONGS TO DADDY"
30 A$="DADDY"
40 ? "DADDY IS AT POSIT. ";
50 ? INSTR(X$, A$, 1)
```

This command returns the beginning of a sub string. The x\$ = the original string. The a\$ = the sub string you want to find. The i = the position in numeric form that you want to search the original string. This command will return the position number where the sub string starts. Spaces are also counted.

Strings and Errors (Cont.):

UINSTR FORMAT: UINSTR(x\$, a\$)
 UINSTR(x\$, a\$, i)
EXAMPLE: 50 ? UINSTR(X\$, A\$)
 20 ? UINSTR(X\$, A\$, 5)

EXAMPLE #2

```
10 DIM X$(40), A$(8)
20 X$="WHERE HAVE ALL THE SOLDIERS GONE"
30 A$="soldiers"
40 ? "soldiers IS AT POSIT";
50 ? UINSTR(X$, A$)
```

EXAMPLE #3

```
10 DIM X$(40), A$(8)
20 X$="ICH BIN EIN BERLINER"
30 A$="berliner"
40 ? "berliner IS AT POSIT.";
50 ? UINSTR(X$, A$, 5)
```

This command is the same as INSTR above. It searches for the beginning of a sub string. x\$=original string. a\$=sub string. i=starting position of the search. With UINSTR you can have lower case, upper case or inverse as the substring. It does not distinguish between case. You can include or eliminate the starting position of the search. See example #2 and #3.

ERR FORMAT: ERR
EXAMPLE: 20 ? ERR
 90 ? "ERROR # ";ERR;" AT LINE ";ERL

EXAMPLE #3

```
10 CLS:DIM A$(15):?:?
20 TRAP 90:READ A$
30 ? A$
40 GOTO 20
50 DATA MONDAY, TUESDAY, WEDNESDAY
60 DATA THURSDAY, FRIDAY
70 DATA SATRUDAY, SUNDAY
90 REM ERROR TRAP ROUTINE
100 ?:"ERROR # ";ERR;" AT LINE ";ERL
110 LIST DPEEK(186):REM LIST ERROR LINE
```

This command lists the last error number.

ERL FORMAT: ERL
EXAMPLE: 20 ? ERL
 90 ? "ERROR # ";ERR;" AT LINE ";ERL

This command prints the line number where the last error occurred. See example #3 at 'ERR'.

Loops and Subroutines:

In Turbo-BASIC XL you call a subroutine in 3 ways:

- 1) GOSUB - by line number.
- 2) PROCEDURE - by name.
- 3) USR - by address.

REPEAT/UNTIL FORMAT: REPEAT - UNTIL - EXIT
EXAMPLE: 10 REPEAT:A=A+1
 20 ? A
 30 UNTIL A=6

EXAMPLE #2

```
10 CLS
20 A=64
30 ?::?:?:?
40 REPEAT:A=A+1
50     ? CHR$(A);", ";
60 UNTIL A=90
```

This command is a loop. It will repeat itself till the end condition is met. The end condition must be included with the UNTIL statement. EXIT gets you out of the loop. See DO-LOOP.

WHILE/WEND FORMAT: WHILE - WEND - EXIT
EXAMPLE: 10 A=10:WHILE A
 20 ? A
 30 A=A-1:WEND

EXAMPLE #2

```
10 CLS:?
20 A=90:WHILE A:? CHR$(A);", ";
30     IF A=65 THEN A=1
40 A=A-1:WEND
```

This command is a loop. As long as the WHILE remains NON-ZERO the loop will execute. All statements between WHILE and WEND will be executed. In example #2, A=A-1 is the reverse counter. We terminate the loop before it becomes zero with the IF-THEN. If you go out of this loop with GOTO use the POP to clear the stack. Example #2 is the same as 'FOR X=90 TO 64 STEP-1'. EXIT gets you out of the loop. See DO-LOOP.

DO/LOOP FORMAT: DO - LOOP - EXIT
EXAMPLE: 10 DO:A=A+1
 20 ? A;", ";
 30 IF A=150 THEN EXIT
 40 LOOP

The DO-LOOP is an infinite loop unless you use the EXIT command to get out of it. The DO and the LOOP are the 2 parts needed for this loop. Anything between them will be printed.

Loops and Subroutines (Cont.):

```
IF/ELSE/ENDIF   FORMAT:      IF - ELSE - ENDIF
                  IF - ENDIF
EXAMPLE:          90 IF X>3:? "TOO LARGE:ELSE:? "OK":ENDIF
                  10 IF A<7 ? "YES":ENDIF
```

EXAMPLE #2

```
10 CLS:?:?
20 INPUT "GIVE ME A NUMBER";A
30 IF A>5
40   PRINT A
50   GO# TOO_BIG
60 ELSE
70   PRINT A
80   GO# A_IS_OK
90 ENDIF
100 # TO_BIG:? "THIS NUMBER IS TOO LARGE":?:GO TO 20
110 # A_IS_OK:? "THIS NUMBER IS JUST RIGHT"
120 END
```

EXAMPLE #3

```
10 CLS:?:?:DIM A$(1)
20 INPUT "IS THIS PORRIDGE OK(Y/N)";A$
30 IF A$(1,1)="N":GO# TOO_HOT:ELSE:GO# JUST_RIGHT:ENDIF
40 # TOO_HOT:?:? "THIS PORRIDGE IS TOO HOT SAID GOLDILOCKS":END
50 # JUST_RIGHT:?:? "THIS IS JUST RIGHT SAID GOLDILOCKS"
```

This command as NO THEN in it. It can be used with an ELSE or not. If you use it on one line be sure to have a colon before and after the ELSE (:ELSE:). This command must be terminated with an :ENDIF. The ENDIF has a colon in front of it if it is used on one line. See example #3 line 30.

Loops and Subroutines (Cont.):

```
PROC/ENDPROC      FORMAT:      PROC - ENDPROC - (EXEC)
EXAMPLE:          10 EXEC START_PROG
                  20 END
                  30 PROC START_PROG
                  40   ? "HELLO"
                  50 ENDPROC
```

EXAMPLE #2

```
10 CLS:?:?
20 EXEC TOO_HARD
30 EXEC TOO_SOFT
40 EXEC JUST_RIGHT
50 END
60 --
70 PROC TOO_HARD
80   ? "GOLDILOCKS SAID THIS BED IS TOO HARD!":?
90 ENDPROC
100 --
110 PROC TOO_SOFT
120  ? "GOLDILOCKS SAID THIS BED IS TOO SOFT!":?
130 ENDPROC
140 --
150 PROC JUST_RIGHT
160  ? "GOLDILOCKS SAID THIS IS JUST RIGHT!"
170 ENDPROC
```

This command is used like GOSUB except we use a variable label name. Just like GOSUB you should have an END statement somewhere in your program. The PROC stand for procedure and is called by the EXEC (execute) command. The EXEC looks for the PROC name and then executes it. The command is terminated with ENDPROC. Anything between PROC and ENDPROC will be executed.

Graphics:

To get a clear understanding of the various graphics modes, colors, screen positions and text windows etc. See the book "YOUR ATARI COMPUTER" by Lon Poole et al. published by Osborne / McGraw-Hill.

CIRCLE FORMAT: CIRCLE x,y,r
EXAMPLE: 40 CIRCLE 160,96,20

EXAMPLE #2

```
10 GRAPHICS 8+16
20 COLOR 1
30 FOR X = 1 TO 90 STEP 3
40   CIRCLE 160,96,X
50 NEXT X
60 GOTO 20
```

EXAMPLE #3

```
10 GRAPHICS 8+16
20 COLOR 1
30 FOR X=20 TO 300 STEP 20
40   CIRCLE X,96,80
50 NEXT X
60 GOTO 20
```

This command draws a circle. The graphic mode has to be stated in the program. x and y are the center position of the circle. r is the radius of the circle.

CIRCLE (Oblique) FORMAT: CIRCLE x,y,r,r2
EXAMPLE: 30 CIRCLE 160,96,50,70

EXAMPLE #2

```
10 GRAPHICS 8+16
20 COLOR 1
30 FOR X=1 TO 75 STEP 3
40   CIRCLE 160,96,X,X+25
50 NEXT X
60 GOTO 20
```

This command is the same as above except we have a vertical radius r2 so we can draw true circles or ellipses. x,y is the center of the circle, r is the radius and r2 is the vertical radius.

Graphics (Cont.):

FCOLOR FORMAT: FCOLOR n
EXAMPLE: 30 FCOLOR 3

EXAMPLE #2

```
10 GRAPHICS 7+16
20 COLOR 1
30 CIRCLE 80,48,45
40 FCOLOR 3
50 FILLTO 80,48
60 FCOLOR 1
70 FILLTO 80,93
80 GOTO 20
```

FCOLOR is usually used in conjunction with the FILLTO command. FCOLOR selects the fill in color. The number of fill in colors depend on the graphics mode.

FILLTO FORMAT: FILLTO x,y
EXAMPLE: 70 FILLTO 80,93

This command fills in a shape with the color selected by the FCOLOR command. It is the same as XIO 18,#6,0,0,"S:". The x and y are the starting position INSIDE the shape. See example #2 under FCOLOR.

PAINT FORMAT: PAINT x,y
EXAMPLE: 40 PAINT 80,48

EXAMPLE #2

```
10 GRAPHICS 7+16
20 COLOR 1
30 CIRCLE 80,48,45
40 PAINT 80,48
50 GOTO 20
```

This is also a type of fill in command. This is a recursive routine that will fill any closed shape. The x and y have to be the position inside the shape to be filled.

TEXT FORMAT: TEXT x,y,a\$
EXAMPLE: 40 TEXT 3,8,A\$

EXAMPLE #2

```
10 CLS
20 DIM A$(4)
30 A$="WIND"
40 TEXT 3,8,A$
```

This command bit-blocks the text in A\$ at position x,y.

Arithmetic and Logic:

HEX\$ FORMAT: HEX\$(n)
 EXAMPLE: 20 ? HEX\$(32)

EXAMPLE #2

```
10 CLS:???:?
20 INPUT "GIVE ME A DECIMAL NUMBER";A
30 ? "DECIMAL ";A;" = HEX ";HEX$(A)
40 ? :GOTO 20
```

This command takes a decimal number and converts it into a HEXIDECIMAL number.

DEC FORMAT: DEC(a\$)
 EXAMPLE: 20 A\$="FF":? DEC(A\$)

EXAMPLE #2

```
10 CLS:???:? : DIM A$(8)
20 INPUT "GIVE ME THE HEX NUMBER";A$
30 ? "HEX ";A$;" = DECIMAL ";DEC(A$)
40 ? :GOTO 20
```

This command changes a HEXIDECIMAL number to a decimal number. The HEX number must first be put into a string. [Note: The HEXIDECIMAL string must be in upper-case in order to be properly converted.]

DIV FORMAT: n DIV i
 EXAMPLE: 20 A=9:B=4:? A DIV B

EXAMPLE #2

```
10 CLS:???:?
20 INPUT "GIVE ME A NUMBER";A
30 INPUT "GIVE ME A SMALLER NUMBER";B
40 Q=A DIV B :R=A MOD B
50 ? A;" / ";B;" = ";
60 ? Q;" REMAINDER ";R
```

This command gives you the whole number part of a division or fraction. Example $9/4=2$ R 1. This command prints the 2.

MOD FORMAT: n MOD i
 EXAMPLE: 20 A=9:B=4:? A MOD B

This command returns the remainder of a division as a whole number. Example $9/4=2$ R 1 This command will print 1. See example #2 above.

Arithmetic and Logic (Cont.):

FRAC FORMAT: FRAC (a)
 EXAMPLE: A=22/7: ? FRAC (A)

 EXAMPLE #2

```
10 CLS:???:?
20 A=22/7
30 ? "THE FRACTION 22/7 = ";A
40 ? "THE DECIMAL PART OF 22/7 = ";FRAC (A)
```

This command prints the decimal part of a fraction ONLY. Example 22/7=3.142857... This command prints 142857...

TRUNC FORMAT: TRUNC (a)
 EXAMPLE: A=22/7: ? TRUNC (A)

 EXAMPLE #2

```
10 CLS:???:?
20 A=22/7
30 ? "THE FRACTION 22/7 =";A
40 ? "THE INTEGER PART =";TRUNC (A)
```

This command prints the Integer part of a fraction ONLY. Example 22/7=3.142857 it will print only 3.

\$nnnn FORMAT: \$nnnn
 EXAMPLE: 20 POKE \$8000

 EXAMPLE #2

```
10 CLS:???:?
20 FOR T = $0F TO $FF
30     ? T; ", ";
40 NEXT T
```

This command allows you to use hexadecimal numbers but they are converted to decimal numbers. In example #2 line 20 is converted to 'FOR T = 15 TO 255'.

Boolean Logic:

The &, !, EXOR, are used in BOOLEAN logic. They are usually used to compare 2 bits. The bits have to be positive. Negative numbers will give you an error. Each program will print out a table for you of the result of comparing 2 bits.

```
&          FORMAT:      n & i
          EXAMPLE:

10 CLS:???:?
20 ? , "BOOLEAN 'AND' (&)"
30 ?
40 ? "BIT ONE", "BIT TWO", "RESULT"
50 ? "1      &", "1 =", 1&1
60 ? "0      &", "1 =", 0&1
70 ? "1      &"; "0 =", 1&0
80 ? "0      &"; "0 =", 0&0
```

This command is the BOOLEAN 'AND'.

```
!          FORMAT:      n ! i
          EXAMPLE:

10 CLS:???:?
20 ? , "BOOLEAN 'OR' (!)"
30 ?
40 ? "BIT ONE", "BIT TWO", "RESULT"
50 ? "1      !", "1 =", 1!1
60 ? "0      !", "1 =", 0!1
70 ? "1      !", "0 =", 1!0
80 ? "0      !", "0 =", 0!0
```

This command is the BOOLEAN 'OR'.

```
EXOR      FORMAT:      n EXOR I
          EXAMPLE:

10 CLS:???:?
20 ? " BOOLEAN 'EXCULSIVE OR' (EXOR)"
30 ?
40 ? "BIT ONE", "BIT TWO", "RESULT"
50 ? "1 EXOR"; "1 =", 1 EXOR 1
60 ? "0 EXOR"; "1 =", 0 EXOR 1
70 ? "1 EXOR", "0 =", 1 EXOR 0
80 ? "0 EXOR", "0 =", 0 EXOR 0
```

This command is the BOOLEAN "Exclusive Or".

Constants:

```
%0 - %3   FORMAT:      %0 %1 %2 %3
          EXAMPLE:
20 X=%1
50 FOR T = %1 TO %3: ? T: NEXT T
```

These 4 constants stand for the numbers 0 to 3. They are used like regular numbers. "X=1" uses 10 bytes while "X=%1" uses 4 bytes. When you use these numbers you save on each number 6 bytes. It is good programming to make variables of numbers that are used more than 3 times.

New Error Codes:

Turbo-BASIC XL prints out in English all errors. You do not have to look up the error code numbers anymore. Turbo-BASIC XL has 8 new error codes not in ATARI-BASIC. The new error codes are form 22 to 30.

FORMAT: Error - 22 ?NEST

The loops are not properly nested

FORMAT: Error - 23 ?WHILE

A WHILE-WEND loop with no corresponding WHILE

FORMAT: Error - 24 ?REPEAT

An UNTIL with no corresponding REPEAT

FORMAT: Error - 25 ?DO

A DO-LOOP with no corresponding DO

FORMAT: Error - 26 ?EXIT

EXIT is outside a loop

FORMAT: Error - 27 ?XPROC

Error in executing a procedure (There is no END line in your program etc.)

FORMAT: Error - 28 ?EXEC

ENDPROC with no corresponding EXEC.

FORMAT: Error - 29 ?PROC

PROC does not exist.

FORMAT: Error - 30 ?#

Variable name label does not exist.

FORMAT: Error - 15

Error 15 has been expanded to include an UNTIL, which is in a REPEAT-UNTIL loop and which has been deleted by mistake.

Self Booting Programs:

If you want to have a program that runs itself upon booting up the disk name it 'AUTORUN.BAS'. Turbo-BASIC XL looks for a BASIC file by this name when the boot process is in operation.

Notes:

Variables, Procedure Names and labels may contain the underscore (_). Now you can combine several words into a name that tells you WHAT and WHERE it goes. This is a powerful feature to make your programs more legible.

EXAMPLES :

```
10 TRAP 200
10 TRAP #END_OF_FILE

60 X = 65
60 # LAST_CHAR = 65

90 IF A$(1,1) = "Y" THEN 60
90 IF A$(1,1) = "Y" THEN # FETCH_LABEL
```

Double Quotes

Double quotes are allowed in print statements. Whenever you want a quote in a print statement put in double quotes.

EXAMPLE :

```
30 ? "SHE SAID ""GOODBYE"" AND SLAMMED THE DOOR"
```

Multiple Line IF-ELSE-ENDIF

You can use several lines between IF and ELSE and ENDIF. See example #2 of IF-ELSE-ENDIF on page 24.

Arrays

You can have only NUMBER arrays. Just like ATARI BASIC, Turbo-BASIC XL does not allow string arrays. Number arrays can be one or two dimensional. You must DIM each array. One dimensional array 'DIM A (5)'. Two dimensional arrays 'DIM A (5,8)'. For a tutorial on arrays and sorting see the back of this disk.

Sorting

For a tutorial on sorting of numbers and strings see the back of this disk.

Public Domain

I am collecting Turbo-BASIC XL utilities to be put into the Public Domain. Your help is appreciated. If you have a utility to share please send it to the author (I prefer it on a disk if possible).

This documentation is in the Public Domain and may be copied by anyone!

The author of this documentation apologizes for any omission or mistakes - they were accidental.



If you cannot get this disk through any Public Domain source please send \$5.00 to the author to cover the expense of the disk, the mailer and postage.

If you have any comments or suggestion about this documentation - they are welcome.

Please write to:

*Ron Fetzer
22 Monaco Ave.
Elmont, NY 11003*

Turbo-BASIC XL Memory Map



The Turbo-BASIC XL Compiler: Documentation and Operating Instructions

by Dave Arlington

Original Program by Frank Ostrowski

This documentation is provided by the Western New York Atari Users Group and may be reprinted freely provided this credit is included.

I know everyone is still rubbing their hands in glee over Turbo-BASIC XL, the new public domain Basic interpreter imported from Holland and Germany. This month we are proud to present a new treat from our international friends overseas, the Turbo-BASIC XL Compiler.

The Turbo-BASIC XL Compiler will increase the speed of your TURBO-BASIC XL programs 3-5 times and regular Atari BASIC programs can be speeded up to 10-15 times faster. Unfortunately, like Turbo-BASIC XL, the Turbo-BASIC XL Compiler will only run on the XL/XE series of computers. In addition, the finished compiled programs will also only run on the XL/XE series.

The Turbo-BASIC XL Compiler is very easy to operate. It can be used with more than one disk drive, even Drive 8, the 130XE ramdisk. On the Turbo-BASIC XL Compiler disk, you will find several files. The important ones for the operation of the Turbo-BASIC XL Compiler are COMPILER.COM and RUNTIME.COM. Before you begin, you should prepare two disks. The first one should be a blank formatted disk with DOS.SYS and DUP.SYS written on it. Your second disk should contain your BASIC program (TURBO or ATARI BASIC).

To begin, insert the Turbo-BASIC XL Compiler disk into your drive and turn your computer on. When it has finished loading you will be in Turbo-BASIC XL. Type DOS to get to the DOS 2.5 menu. Choose DOS Option 'L', Load Binary File and load the file COMPILER.COM. After a short while, you will see a screen full of German. If you do not read German, do not worry, that is what this article is for! At any time that you are on this screen, you may reboot your system by hitting Control-R or you may return to DOS by hitting Control-D. You will be asked if you really want to do this. If you do, don't forget to 'J' for Ja and not 'Y' for Yes!!

To compile your programs, remove the Turbo-BASIC XL Compiler disk from the drive and insert the disk with the program you want to compile. (If you have two drives, insert your disk with the program to compile in Drive 2 and the blank DOS disk in Drive 1.) Press the number 1 key (Number 2 if you have two drives). A complete listing of all the files on that drive will appear on the screen with one highlighted in inverse video. Using the arrow keys, highlight the file you want to compile and hit Return. That's all there is to it!

At the top of the screen, you will see the line numbers fly by as the program is compiled. When it is finished, you will be prompted for a file name to save your compiled program under. It has to have an extender of CTB (for Compiled Turbo Basic). The program will not let you use any other extender. At this time, if you have one drive, you should remove your disk with your original program on it and replace it with your blank DOS disk. If you want your compiled program to be an AUTORUN file, you should name it AUTORUN.CTB. Then the file will automatically load and run at bootup time.

There is one more step that you must do to get a completely runnable compiled program. Go back to DOS and copy the file RUNTIME.COM from the Turbo-BASIC XL Compiler disk to the disk with your compiled program on it. Rename the RUNTIME.COM file to the name AUTORUN.SYS. Your disk is now ready to go. The Turbo-BASIC XL Compiler does not compile to runnable code, you must run the RUNTIME.COM file to run your compiled program.

One technical note on the Turbo-BASIC XL Compiler: If you're not familiar with other compilers for the ATARI computers, you should know that many have trouble compiling certain types of statements or insist that you organize your program structure in a certain way. So far none of these problems have occurred on any programs we have tested with the Turbo-BASIC XL Compiler. The only statement that wouldn't compile so far is the END statement. The only program structure that we have had trouble with is a FOR-NEXT loop that has two or more NEXTs for one FOR.

For example:

```
10 FOR X=1 TO 5
20     IF X=3 THEN NEXT X
30 NEXT X
```

Other than those two examples, we have had no problems compiling any type of program, either TURBO or ATARI BASIC. Please let us know of any problems you run into compiling any types of statements or programs.

Whether you program in Turbo-BASIC XL or just want to turbo-charge your old Atari BASIC programs to super speed, I'm sure you will find the Turbo-BASIC XL Compiler will fit all your speed needs.

Turbo-BASIC XL Commands: Quick Reference

Disk Commands:

BLOAD *"Dn:FileSpec"*
BRUN *"Dn:FileSpec"*
DELETE *"Dn:FileSpec"*
DIR [*optional "Dn:FileSpec"*]
LOCK *"Dn:FileSpec"*
RENAME *"Dn:OldFilename.ext, NewFilename.ext"*
UNLOCK *"Dn:FileSpec"*

Memory:

DPEEK (*Memory Location*)
DPOKE *Memory Location, Value*
MOVE *Source MemLoc, Destination MemLoc, NumBytes*
-MOVE *Source MemLoc, Destination MemLoc, NumBytes*
[note: starts with last byte]
BGET *#Channel, Destination MemLoc, NumBytes*
BPUT *#Channel, Source MemLoc, NumBytes*
%GET *#Channel, Floating Point Value*
%PUT *#Channel, Floating Point Value*

Structured Programming:

REPEAT (*Program Code*) UNTIL
WHILE (*Program Code*) WEND
IF (*Program Code*)
ELSE (*Program Code*) ENDIF
DO (*Program Code*) LOOP
EXIT (exit from a structured loop)
PROC *Procedure Name (Program Code) ENDPROC*
EXEC *Procedure Name (execute a procedure)*

Programming Utilities:

PAUSE *Value (in jiffies)*
RENUM *Starting Line, Starting Number, Increment*
DEL *First Line, Last Line*
DUMP [*optional Device*]
TRACE (turn program tracing ON)
TRACE- (turn program tracing OFF)
DSOUND *Note, Frequency, Distortion, Volume*
(pairs audio registers together for extended range)
DSOUND (turns Off sounds)
*L (turns ON line indent)
*L- (turns OFF line indent)
*F (Turbo-BASIC FOR/NEXT)
*F- (Atari BASIC FOR/NEXT)
*B (traps the <Break> key)
*B- (untraps the <Break> key)
-- (special REM displaying 30 dashes)
Label Name (line label)
GO# *Label Name (go to a line label)*

Graphics:

CIRCLE *X, Y, R, [optional R2 (vertical radius)]*
FCOLOR *Color# (fill color)*
FILLTO *X, Y (same as XIO #6)*
PAINT *X, Y (fills an enclosed shape)*
TEXT *X, Y, A\$ (bit-blocks text)*

Modifications of Atari Commands:

CLOSE (closes channels #1 - #7)
DIM (zeroes arrays with null strings)
GET *Variable Name (gets value from "K:")*
INPUT *"Prompt"; VarName or "Prompt", VarName*
[note: semi-colon uses "?" prompt,
comma uses no prompt]
INPUT *Variable Name [note: uses "?" prompt]*
LIST *Start Line, [optional End Line]*
[note: lists to program end when
optional end line is not present]
ON *Value EXEC Proc1, Proc2, etc...*
PUT *ATASCII Value (same as ? CHR\$(ATASCII Value))*
RESTORE *#Label Name*
RND [note: (0) is now optional]
SOUND [note: turns off all sounds]
TRAP *#Label Name*

Arithmetic & Logic:

HEX\$ (*Value*) (converts decimal *Value* to hexadecimal)
DEC (*HexString\$*) (converts hexadecimal string to decimal)
[note: string must be in all upper-case]
DIV *Value1 DIV Value2* (integer quotient)
MOD *Value1 MOD Value2* (remainder of *Value1/Value2*)
FRAC (*Value*) (gives fractional part of *Value*)
TRUNC (*Value*) (truncates *Value*)
RAND (*Value*) (random integer from zero to *Value-1*)
\$ *Value* (allows hex entry from \$0 - \$FFFF)
& *Value1 & Value2* (bitwise "AND")
! *Value1 ! Value2* (bitwise "OR")
EXOR *Value1 EXOR Value2* (bitwise "Exclusive OR")

Strings, Errors, & Constants:

TIME (elapsed time in jiffies since computer was
turned on, or last time <RESET> was pressed)
TIME\$ (returns time in the form: "HHMMSS")
INKEY\$ (returns the last key pressed)
INSTR (*String\$, SubString\$, [optional Start Position]*)
UINSTR (*String\$, SubString\$, [optional Start Position]*)
[note: not case-sensitive]
ERR (returns the last error number)
ERL (returns the last error line)
[note: TBXL doesn't automatically clear either
ERR or ERL]
%0 - %3 (constants, saving 6 bytes each time used in variable
assignment compared to using numerical values)

General Notes:

- Use *""Text""* (double-quotes) in PRINT statements to render as single quotes.
- Turbo-BASIC XL looks for "AUTORUN.BAS" at boot-up.
- Variables, Procedure Names, and Labels may use the underscore "_" character.
- Patched U.S. version of Turbo-BASIC XL has the prompt "TURBO" instead of "READY".
- New Turbo-BASIC XL error Messages are #23 - #30, most of which are related to loops, nesting, and procedures.